

Introduction to Parallel Performance Engineering

Alan O'Cais

Jülich Supercomputing Centre

(with content used with permission from tutorials by Markus Geimer, Brian Wylie, Bernd Mohr/JSC and Luiz DeRose/Cray)





















Performance: an old problem





Difference Engine


"The most constant difficulty in contriving the engine has arisen from the desire to reduce the time in which the calculations were executed to the shortest which is possible."

> Charles Babbage 1791 – 1871

Today: the "free lunch" is over



- Moore's law is still in charge, but
 - Clock rates no longer increase
 - Performance gains only through increased parallelism
- Optimizations of applications more difficult
 - Increasing application complexity
 - Multi-physics
 - Multi-scale
 - Increasing machine complexity
 - Hierarchical networks / memory
 - More CPUs / multi-core




F Every doubling of scale reveals a new bottleneck!


Example: XNS




- CFD simulation of unsteady flows
 - Developed by CATS / RWTH Aachen
 - Exploits finite-element techniques, unstructured 3D meshes, iterative solution strategies
- MPI parallel version
 - >40,000 lines of Fortran & C
 - DeBakey blood-pump data set (3,714,611 elements)



Partitioned finite-element mesh







Performance factors of parallel applications



- "Sequential" factors
 - Computation
 - F Choose right algorithm, use optimizing compiler
 - Cache and memory
 - F Tough! Only limited tool support, hope compiler gets it right
 - Input / output
 - F Often not given enough attention
- "Parallel" factors
 - Partitioning / decomposition
 - Communication (i.e., message passing)
 - Multithreading
 - Synchronization / locking
 - F More or less understood, good tool support

Tuning basics



- Successful engineering is a combination of
 - The right algorithms and libraries
 - Compiler flags and directives
 - Thinking !!!
- Measurement is better than guessing
 - To determine performance bottlenecks
 - To compare alternatives
 - To validate tuning decisions and optimizations F After each step!




"We should forget about small efficiencies, say 97% of the time: premature optimization is the root of all evil."

Charles A. R. Hoare

- It's easier to optimize a slow correct program than to debug a fast incorrect one
 - F Nobody cares how fast you can compute a wrong answer...

Performance engineering workflow





- Prepare application (with symbols), insert extra code (probes/hooks)
- Collection of data relevant to execution performance analysis
- Calculation of metrics, identification of performance metrics
- Presentation of results in an intuitive/understandable form
- Modifications intended to eliminate/reduce performance problems

The 80/20 rule



- Programs typically spend 80% of their time in 20% of the code
- Programmers typically spend 20% of their effort to get 80% of the total speedup possible for the application
 - F Know when to stop!
- Don't optimize what does not matter
 - F Make the common case fast!

"If you optimize everything, you will always be unhappy."

Donald E. Knuth

Metrics of performance



- What can be measured?
 - A count of how often an event occurs
 - E.g., the number of MPI point-to-point messages sent
 - The duration of some interval
 - E.g., the time spent these send calls
 - The size of some parameter
 - E.g., the number of bytes transmitted by these calls
- Derived metrics
 - E.g., rates / throughput
 - Needed for normalization

Example metrics



- Execution time
- Number of function calls
- CPI
 - CPU cycles per instruction
- FLOPS
 - Floating-point operations executed per second

"math" Operations?
HW Operations?
HW Instructions?
32-/64-bit? ...

Execution time



Wall-clock time

- Includes waiting time: I/O, memory, other system activities
- In time-sharing environments also the time consumed by other applications

CPU time

- Time spent by the CPU to execute the application
- Does not include time the program was context-switched out
 - Problem: Does not include inherent waiting time (e.g., I/O)
 - Problem: Portability? What is user, what is system time?


Problem: Execution time is non-deterministic

Use mean or minimum of several runs

Inclusive vs. Exclusive values



- Inclusive
 - Information of all sub-elements aggregated into single value
- Exclusive
 - Information cannot be subdivided further




Classification of measurement techniques



- How are performance measurements triggered?
 - Sampling
 - Code instrumentation
- How is performance data recorded?
 - Profiling / Runtime summarization
 - Tracing
- How is performance data analyzed?
 - Online
 - Post mortem

Sampling






```
int main()
  int i;
  for (i=0; i < 3; i++)
    foo(i);
  return 0;
void foo(int i)
  if (i > 0)
    foo(i - 1);
```

- Running program is periodically interrupted to take measurement
 - Timer interrupt, OS signal, or HWC overflow
 - Service routine examines return-address stack
 - Addresses are mapped to routines using symbol table information
- Statistical inference of program behavior
 - Not very detailed information on highly volatile metrics
 - Requires long-running applications
- Works with unmodified executables

Instrumentation





```
int main()
  int i;
  Enter("main");
  for (i=0; i < 3; i++)
    foo(i);
  Leave("main");
  return 0;
void foo(int i)
  Enter("foo");
  if (i > 0)
    foo(i - 1);
  Leave("foo");
```

- Measurement code is inserted such that every event of interest is captured directly
 - Can be done in various ways
- Advantage:
 - Much more detailed information
- Disadvantage:
 - Processing of source-code / executable necessary
 - Large relative overheads for small functions

Instrumentation techniques



- Static instrumentation
 - Program is instrumented prior to execution
- Dynamic instrumentation
 - Program is instrumented at runtime
- Code is inserted
 - Manually
 - Automatically
 - By a preprocessor / source-to-source translation tool
 - By a compiler
 - By linking against a pre-instrumented library / runtime system
 - By binary-rewrite / dynamic instrumentation tool

Critical issues



Accuracy

- Intrusion overhead
 - Measurement itself needs time and thus lowers performance
- Perturbation
 - Measurement alters program behaviour
 - E.g., memory access pattern
- Accuracy of timers & counters

Granularity

- How many measurements?
- How much information / processing during each measurement?

F Tradeoff: Accuracy vs. Expressiveness of data

Classification of measurement techniques



- How are performance measurements triggered?
 - Sampling
 - Code instrumentation
- How is performance data recorded?
 - Profiling / Runtime summarization
 - Tracing
- How is performance data analyzed?
 - Online
 - Post mortem

Profiling / Runtime summarization



- Recording of aggregated information
 - Total, maximum, minimum, ...
- For measurements
 - Time
 - Counts
 - Function calls
 - Bytes transferred
 - Hardware counters
- Over program and system entities
 - Functions, call sites, basic blocks, loops, ...
 - Processes, threads

F Profile = summarization of events over execution interval

Types of profiles



Flat profile

- Shows distribution of metrics per routine / instrumented region
- Calling context is not taken into account

Call-path profile

- Shows distribution of metrics per executed call path
- Sometimes only distinguished by partial calling context (e.g., two levels)

Special-purpose profiles


- Focus on specific aspects, e.g., MPI calls or OpenMP constructs
- Comparing processes/threads

Tracing



- Recording information about significant points (events) during execution of the program
 - Enter / leave of a region (function, loop, ...)
 - Send / receive a message, ...
- Save information in event record
 - Timestamp, location, event type
 - Plus event-specific information (e.g., communicator, sender / receiver, ...)
- Abstract execution model on level of defined events

F Event trace = Chronologically ordered sequence of event records



Tracing vs. Profiling



Tracing advantages

- Event traces preserve the temporal and spatial relationships among individual events (F context)
- Allows reconstruction of dynamic application behaviour on any required level of abstraction
- Most general measurement technique
 - Profile data can be reconstructed from event traces

Disadvantages

- Traces can very quickly become extremely large
- Writing events to file at runtime causes perturbation
- Writing tracing software is complicated
 - Event buffering, clock synchronization, ...

Classification of measurement techniques



- How are performance measurements triggered?
 - Sampling
 - Code instrumentation
- How is performance data recorded?
 - Profiling / Runtime summarization
 - Tracing
- How is performance data analyzed?
 - Online
 - Post mortem

Online analysis



- Performance data is processed during measurement run
 - Process-local profile aggregation
 - More sophisticated inter-process analysis using
 - "Piggyback" messages
 - Hierarchical network of analysis agents
- Inter-process analysis often involves application steering to interrupt and re-configure the measurement


Post-mortem analysis




- Performance data is stored at end of measurement run
- Data analysis is performed afterwards
 - Automatic search for bottlenecks
 - Visual trace analysis
 - Calculation of statistics


Example: Time-line visualization








58	Α	ENTER	1
60	В	ENTER	2
62	Α	SEND	В
64	Α	EXIT	1
68	В	RECV	Α
69	В	EXIT	2







F A combination of different methods, tools and techniques is typically needed!

- Analysis
 - Statistics, visualization, automatic analysis, data mining, ...
- Measurement
 - Sampling / instrumentation, profiling / tracing, ...
- Instrumentation
 - Source code / binary, manual / automatic, ...

Typical performance analysis procedure



- Do I have a performance problem at all?
 - Time / speedup / scalability measurements
- What is the key bottleneck (computation / communication)?
 - MPI / OpenMP / flat profiling
- Where is the key bottleneck?
 - Call-path profiling, detailed basic block profiling
- Why is it there?
 - Hardware counter analysis, trace selected parts to keep trace size manageable
- Does the code have scalability problems?
 - Load imbalance analysis, compare profiles at various sizes function-by-function